WIRELESS PRINTING MACINTOSH OS X 10.7 and up

WHAT IS WIRELESS PRINTING?

Wireless printing allows you to print documents from your laptop to selected campus printers while connected to the U of T campus wireless network. Wireless printing costs the same as regular printing for the print location you have chosen.

HOW DOES IT WORK?


You must be connected to the U of T wireless network when you print your documents (see http://wireless.utoronto.ca for instructions). You will modify your System Preferences to add the printer, then print the document to the printer you specified. Insert your TCard into the card reader beside the printer, select your document from the list, and collect your printout.

PART 1: ADDING A NEW PRINTER

- 1. Click on the **Apple** menu and choose **System Preferences**.
- 2. Click the Printers & Scanners icon.



3. Click the `+` icon to add a new printer. You may need to click the lock (bottom left corner) before the + sign is available.



4. In the Printer Browser window, go to the IP settings and add the information shown in bold below in the corresponding fields:

Address: printhere.utoronto.ca Queue: PR-Colour Name : Pratt Colour Printer (1st Floor)

printhere.utoronto.ca	Default Fax	IP V	Vindows Blueto	oth AppleTalk	More Printers	Q. Search
Queue: PR-Colour	Protocol	I: Line	Printer Daem	on – LPD		•
Name : Pratt Colour Printer	Address:		here.utoronto nd complete add			
(1st Floor)	Queue:		W blank for default	queue.		
For settings for other locations, go	Name	Roba	irts InfoComm	ions B&W Prir	nters	
to http://printhere.utoronto.ca/	Location: Print Using		eric PostScript	Printer		
macprinting.html.						
					•	Add

- 5. Click the **Add** button to complete the configuration.
- Quit System Preferences. 6.

PART 2: PRINTING

1. Make sure you are connected to the Internet and open the document you wish to print.

E.J. Pratt Library – Colour printer

- 2. From the File menu choose Print.
- 3. Select the desired (wireless) printer location from the pull-down

Printer:	Robarts 1st Floor	
Presets:	Standard	•
	Copies & Pages	*
Copies:	1 Collated	
Pages:	• All • From: 1 to: 1	_
	O From: 1 0: 1	
? PDF • Pre	view	Cancel Print

menu in the Print window.

- 4. Set any other page settings you need, and click **Print**.
- 5. Go to the print location. Insert your TCard or Library smart card in the print-release card reader.
- 6. A list of print jobs will appear on the screen. Your job will display the name of the file. Select it and click Print.
- Retrieve your card after the cash balance has been updated. 7.

Jobs that are left in the queue will be deleted after 30 minutes.

SUPPORT

If you have difficulty installing or using the wireless printing service, visit the Information Commons Help Desk, ground floor of Robarts Library. See http://help.ic.utoronto.ca/ for hours of service.

ADDITIONAL INFORMATION

Technically, you only need an Internet connection—it doesn't have to be wireless. For example, you could install this software on your Internetcon-nected desktop computer in residence. You could then print a document to a selected printer, and walk over to retrieve the output.